MAJOR NECTAR WINTER SPRING BUILDUP FALL CANADIAN HONEY COUNCIL VARROA MITE (VARROA DESTRUCTOR) - VM SEASONAL MONITORING & TREATMENT CULTURAL CONTROL ALCOHOL WASH OR STICKY BOARDS.
MONITOR FOR ACARACIDE RESISTANCE EFFECTIVE ECONOMICAL AND IF MITE LEVELS ARE HIGH TREAT WITH FOR-ENVIRONMENTALLY-SOUND TRACHEAL MITE (ACARAPIS WOODI) - HBTM Using CULTURAL AND PHYSICAL PRACTICES to CULTURAL CONTROL MONITORING AND IDENTIFYING before they reach an SEND SAMPLE OF 150 BEES TO LAB FOR TESTING FOR TRACHEAL MITES. TREATING through a combination of suppress to acceptable levels IF MITE LEVELS GREATER THAN 10% TREAT WITH FOR-MIC AGID OR MENTHOL. IF TRACHEAL MITE INFESTATION IS GREATER EVALUATING THE EFFICACY of AMERICAN FOULBROOD (PAENIBACILLUS LARVAE SP) - AFB IPM FOR BEEKEEPERS CHECK THAT THE TREATMENT WORKED **CULTURAL CONTROL** DIFFING TO FALL:
CHICOGO TO FALL:
AND DEAD LARVAE THAT AR
STICKY TO ROPEY TEXTURE SEND AFB SAMPLES TO LAB FOR TESTING FOR ANTIBIOTIC RESISTANCE. FALL TREATMENT WITH OXYTETRACYCLINE IF AFB IS PRESENT, STERILIZE WOOD EQUIPMENT WITH HOT PARAFFIN WAX OR STERILIZE FRAMES AND BOX USING ELEC-NOSEMA (NOSEMA APIS & NOSEMA CERANAE) - NO AVOID MOVING HIVES DURING WINTER, PROVIDE HIGH PROTEIN POLLEN SOURCE FOR WINTER SURVIVAL REPLACE AT LEAST 2 FRAMES OF OLD BROOD COMB WITH NEW IN LATE SPRIN AND SUMMER. CULTURAL CONTROL De Rob Carrie University of Mariada. OBSERVE BEES FOR SIGNS OF DYSENTERY, DISTENDED ABDOMENS OR UNHOCKED WINGS. MONITOR THE SPORE LEVELS IN SPRING BY SENDING A SAMPLE OF 150 BEES TO A LAB FOR TESTING. MONITOR IN FALL, IF MORE THAN I MILLION SPORES PER BEE BEGIN TREATMENT. IF MORE THAN 1 MILLION SPORES/BEE BEGIN TREATMENT. FEED ONE GALLON SUGAR SYRUP WITH FUMAGILLIN SPRING BOITHER COLUMBIA BC Hinistry of Agriculture & Lands' Animal Health Centre 1707 Angus Campball Rd Abadeked IIC 1/20 290 LABS AND TESTING Laboratory Services 95 Stana Relitions, Quelph, CN NTH BUT 1 Brush two or three frames of bees into a tub, taking Previncial Apiculturist Alberts Agriculture and Food, Econoston AB **FACILITIES** lotron Technologies Canada Inc 1425 Kelet Way Port Cogultum BC VSC 6L5 684-945-6030 -N N1H 8J7 hone 519-767-6209 or emel Pour the bees into a mason jar. Tap the glass to knock the bees to the bottom of the jar. 4 Spray starter fluid into the jar and shake the jar Allson Skinner OllA Tech Transfer program Tanglewood Honey Bee Lab Amirault's See Lab Sudbec Jaboratoire d'Épidémiesur-veitthoroughly.

5 The heavy bees fall to the bottom of the jar, the lighter mites will stick to the walls allowing you to count Honey Bee Disease and Pests. Manifeba Agriculture Food and Flural Initiatives Provincial Apoultarist or Bee Health Advisor NS 902-073-0900, NS 500-453-3477, PE 902-369-9021,NL, 700forsel Indicatores Apriculture Lab. 201-545 University Dr. Wyrripeg, 14th 807-556 Phone 204-645-5601